

Range Breakout EA Inputs:

<Volume Settings>

Trading Volume: Mode for the calculation of the lot size for each trade

Fixed Lots: Lot size for each trade if the fixed trading volume mode is chosen

Fixed Lots Per x Money: Uses "Fixed Lots" per each x amount of money in your trading account

Risk Percentage of Base Money: The lot size for each trade will be calculated so that the set percentage of the Base Money input will be lost if the initial SL is triggered

Base Money: Used for the lot calculation in the percentage mode

<Order Settings>

Order Puffer Points (0 = No Puffer): Orders will be placed x points above and below the range

Target Factor (0 = No TP): The distance form the entry order price to the TP calculated as a multiple of the current range

Stop Factor (0 = No SL): The distance form the entry order price to the SL calculated as a multiple of the current range

<Time Settings>

Range Start Hour: Hour for the start time of the daily range

Range Start Minute: Minute for the start time of the daily range

Range End Hour: Hour for the end time of the daily range

Range End Minute: Minute for the end time of the daily range

Delete Orders Hour: Hour for the expiration time of pending orders

Delete Orders Minute: Minute for the expiration time of pending orders

Close Positions: Decides if open positions are closed at the close position time

Close Positions Hour: Hour for the close time of open positions

Close Positions Minute: Minute for the close time of open positions

<Trailing Stop Settings>

BE Stop Trigger Percent (0 = Inactive): The Break Even Stop is activated as soon as a trade is more than the BE Stop Trigger Percent in profit

BE Stop Puffer Percent: The Break Even Stop will move the Stop Loss BE Stop Puffer Percent in profit once it is activated

TSL Trigger Percent (0 = Inactive): The Trailing Stop is activated as soon as a trade is more than the TSL Trigger Percent in profit

TSL Percent: The Trailing Stop will be trailed in this set distance behind the current market price

TSL Step Percent: The SL will only be modified if it is at least this distance above the previous SL

The percentage is always based on the position open price!

<Trading Frequency Settings>

Max Long Trades: Maximum amount of buy trades on a single day

Max Short Trades: Maximum amount of sell trades on a single day

Max Total Trades: Maximum amount of trades on a single day

<Range Filter Settings>

Min Range Percent: Ranges are ignored if they are smaller than the Min Range Percent

Max Range Percent: Ranges are ignored if they are bigger than the Max Range Percent

The percentage is always based on the current range high!

<More Settings>

Object Color: Color of the chart objects (range & chart comment)

Order Comment: Commentary for every order the EA places

Magic Number: This number should be unique for every EA in your account since the EAs use it to identify their own trades

Chart Comment: Activates or deactivates the comment in the upper left corner of the chart