

Turnaround Tuesday EA Inputs:

(Trading Volume Modes):

VOLUME_FIXED > Uses a fixed lot size for every trade

VOLUME_MANAGED > Uses "Fixed Lots" per each „Fixed Lots Per x Money“ amount of money in your trading account

VOLUME_PERCENT > The lot size will be calculated so that the set percentage of your account will be lost if the initial SL is triggered

VOLUME_MONEY > The lot size will be calculated so that the set amount of money will be lost if the initial SL is triggered

(TP, SL and TSL Calculation Modes):

CALC_MODE_OFF > TP/SL/TSL is not used

CALC_MODE_PERCENT > Distance is a percentage of the entry price

CALC_MODE_POINTS > Distance is set in points. One point is always the smallest price change for the current symbol, e.g. EURUSD, 5 digits > 1 point = 0.00001 or US30, 2 digits > 1 point = 0.01

<General Settings>

Wait For New Day High: Orders will be sent once there is a new daily high if this input is 'true'. When 'false' it will send the order immediately at the start time.

Trading Volume: Mode for the calculation of the lot size for each trade

Fixed Lots: Lot size for VOLUME_FIXED and VOLUME_MANAGED

Fixed Lots Per x Money: Base amount for VOLUME_MANAGED

Risk Percentage of Balance: Risk percent for VOLUME_PERCENT

Risk Money: Risk amount for VOLUME_MONEY

Target Calc Mode: Calculation mode for the TP distance (entry to TP)

Target Value: Value for the TP calculation based on the Target Calc Mode

Stop Calc Mode: Calculation mode for the SL distance (entry to SL)

Stop Value: Value for the SL calculation based on the Stop Calc Mode

<Time Settings>

Trading Start Hour: Hour for the trading start time

Trading Start Minute: Minute for the trading start time

Position Close Hour: Hour for the close time of open positions

Position Close Minute: Minute for the close time of open positions

Open Day of Week: Trades will be opened on this weekday

Close Day of Week: Trades will be closed on this weekday

<Trailing Stop Settings>

BE Calc Mode: Calculation mode for the break even stop

BE Stop Trigger Value: The Break Even Stop is activated as soon as a trade is more than the BE Stop Trigger Value in profit

BE Stop Buffer Value: The Break Even Stop will move the stop loss BE Stop Puffer Value in profit once it is activated

TSL Calc Mode: Calculation mode for the classic trailing stop

TSL Trigger Value: The Trailing Stop is activated as soon as a trade is more than the TSL Trigger Value in profit

TSL Value: The Trailing Stop will be trailed in this set distance behind the current market price

TSL Step Value: The SL will only be modified if it is at least this distance above the previous SL

<Indicator Settings>

Use MA Filter: Activates or deactivates the MA Filter

MA Filter Timeframe: Timeframe for the MA Filter

MA Filter Periods: Periods for the MA Filter

MA Filter Method: Method for the MA Filter

Ma Filter Applied Price: Applied Price for the MA Filter

<More Settings>

Order Comment: Commentary for every order the EA places

Magic Number: This number should be unique for every EA in your account since the EAs use it to identify their own trades

Chart Comment: Activates or deactivates the comment in the upper left corner of the chart